


This guide will show you how to configure MagicJack to work with Http-Tunnel.

Do Not have MagicJack Plugged in at this time. You will also need a 3rd Party application: Proxifer


Once you have Http-Tunnel installed, run the application, The main window will appear, choose the configure option. There you will be presented with three (3) options.

1. You can Select Auto detect if you want Http-Tunnel to detect your settings.
 2. No Proxy only a firewall if this is appropriate.
 3. Specify Proxy, Here you will enter the IP address and Port number of the proxy that you use.
- Complete 1 of the 3 options, then click test, the client will bind to port 1080 and localhost by default and connect to the tunnel servers if your settings are correct.




Download and install Proxifier:

Run Proxifier. On the Menu bar choose Options, a pull down list should appear, select 'Proxy Settings'. The Proxy Settings window should appear.



On the Proxy Settings window 'Click' the Add button, The Proxy Server window should appear. In the IP field type in 127.0.0.1 or (localhost) 127.0.0.1 works best in most cases. Then enter 1080 in the Port field. Select 1 of the 3 protocols to use, either SOCKS 4/5 or HTTP. Experimenting with these setting may determine which works best for you. If you are using a Proxy and it requires authentication be sure to fill in the proper fields. After you have completed entering in the appropriate values 'Click' the OK's as you exit.


Next: On the Proxifier menu bar 'Click' Options. A pull down list should appear. Select: Proxification Rules and 'Click' on it.



The 'Proxification Rules' window should appear. Put a 'dot' in 'Proxy All except the following + manually proxyify'. Next 'Click' on the Add button the 'Edit Proxification Rule' window should appear. In 'Rule Name' field give a name to your rule. I named the one for the client 'HTTPTunnel' as you can see. Then 'Click' the Add button in the 'Edit Proxification Rule' window. A window titled Open should appear. This allows you to browse your computer for files. Use the window to browse for the 'HTTP-TunnelClient' exe file. Click on the 'HTTP-TunnelClient' exe file to high-light it. Then 'Click' Open on the window titled Open. You will then see the file has now been loaded into the 'Edit Proxification Rule' window. 'Click' OK on the 'Edit Proxification Rule' window. And then 'Click' OK on the 'Proxification Rules' window. You have now completed the set-up of Proxifier. You may want to shut down all applications including the tunnel client and Proxifier. Next: restart the tunnel client and then Proxifier. Most of the times it will not matter. Proxifier is able to accommodate just about any start up sequence.

Next: Plug in the MagicJack. Next " Click " The MagicJack desktop icon.

You should now see MagicJack connecting through Proxifier and the HTTPTunnel client.



But remember now. Everything but the tunnel client is now proxified. This configuration will give MagicJack the best chance of working. You can exclude other applications the same way as you excluded the tunnel client. Your Browsers, IMs, P2P, etc. will go through Proxifier if you do not exlude those and could interfere with MagicJack.